

# Outlook Setup Guide – 2007, 2010 or 2013

The following guide should help you make your way through setting up Outlook. This guide will work with Outlook 2007, 2010 and 2013 as they're all very similar Outlook clients. If you have any trouble, please don't hesitate to let me know and I'll be happy to walk you through it.

## IMAP Email Setup Guide

Username: Full email address (example: [bob@drbob.com](mailto:bob@drbob.com))

Hostname: secure.emailsrvr.com

Incoming Port: 993

Outgoing Port: 465

SSL: Enabled



Account Configuration

**E-mail Accounts**

You can configure Outlook to connect to Internet E-mail, Microsoft Exchange, or other E-mail server. Would you like to configure an E-mail account?

Yes  
 No

< Back   Next >   Cancel

Add New Account

**Auto Account Setup**  
Connect to other server types.

**E-mail Account**

Your Name:   
Example: Ellen Adams

E-mail Address:   
Example: ellen@contoso.com

Password:   
Retype Password:   
Type the password your Internet service provider has given you.

**Text Messaging (SMS)**

**Manually configure server settings or additional server types**

< Back   Next >   Cancel

Add New Account

**Choose Service**

**Internet E-mail**  
Connect to POP or IMAP server to send and receive e-mail messages.

**Microsoft Exchange or compatible service**  
Connect and access e-mail messages, calendar, contacts, faxes and voice mail messages.

**Text Messaging (SMS)**  
Connect to a mobile messaging service.

Add New Account

**Internet E-mail Settings**  
Each of these settings are required to get your e-mail account working.

<p><b>User Information</b></p> <p>Your Name: <input type="text" value="Your Full Name"/></p> <p>E-mail Address: <input type="text" value="email@email.com"/></p> <p><b>Server Information</b></p> <p>Account Type: <input type="text" value="IMAP"/></p> <p>Incoming mail server: <input type="text" value="secure.emailsrvr.com"/></p> <p>Outgoing mail server (SMTP): <input type="text" value="secure.emailsrvr.com"/></p> <p><b>Logon Information</b></p> <p>User Name: <input type="text" value="fullemailaddress@email.com"/></p> <p>Password: <input type="password" value="*****"/></p> <p><input checked="" type="checkbox"/> Remember password</p> <p><input type="checkbox"/> Require logon using Secure Password Authentication (SPA)</p>	<p><b>Test Account Settings</b></p> <p><input type="button" value=" Test Account Settings ..."/></p> <p>1) Your Full Name or Business Name 2) Your Full Email Address</p> <p>3) Always select IMAP 4) Both servers should be: secure.emailsrvr.com</p> <p>5) Username is your FULL email address again 6) Your password - select remember password</p> <p><input type="button" value=" More Settings ..."/></p>
---	---

Internet E-mail Settings

General	Sent Items	Deleted Items
Outgoing Server	Connection	Advanced

My outgoing server (SMTP) requires authentication  
 Use same settings as my incoming mail server  
 Log on using  
User Name:   
Password:   
 Remember password  
 Require Secure Password Authentication (SPA)

1) Select "Outgoing Server"  
2) Check off "My outgoing server (SMTP) requires authentication"  
- Use same settings as my incoming mail server

OK Cancel

Internet E-mail Settings

General	Sent Items	Deleted Items
Outgoing Server	Connection	Advanced

Server Port Numbers

Incoming server (IMAP): 993 Use Defaults  
Use the following type of encrypted connection: SSL

Outgoing server (SMTP): 465  
Use the following type of encrypted connection: SSL

Server Timeouts  
Short Long 1 minute

Folders  
Root folder path:

1) SSL selected in both areas  
2) Incoming server (IMAP): 993  
3) Outgoing server (SMTP): 465

Click "OK" when done.

OK Cancel

